


External Backup Tools: SAP DB



Copyright

© Copyright 2003 SAP AG.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1 or any later version published by the Free Software Foundation.

For more information on the GNU Free Documentaton License see <http://www.gnu.org/copyleft/fdl.html#SEC4>.

Icons

Icon	Meaning
	Caution
	Example
	Note
	Recommendation
	Syntax

Typographic Conventions

Type Style	Description
<i>Example text</i>	Words or characters that appear on the screen. These include field names, screen titles, pushbuttons as well as menu names, paths and options. Cross-references to other documentation.
Example text	Emphasized words or phrases in body text, titles of graphics and tables.
EXAMPLE TEXT	Names of elements in the system. These include report names, program names, transaction codes, table names, and individual key words of a programming language, when surrounded by body text, for example, SELECT and INCLUDE.
Example text	Screen output. This includes file and directory names and their paths, messages, source code, names of variables and parameters as well as names of installation, upgrade and database tools.
EXAMPLE TEXT	Keys on the keyboard, for example, function keys (such as F2) or the ENTER key.
Example text	Exact user entry. These are words or characters that you enter in the system exactly as they appear in the documentation.
<Example text>	Variable user entry. Pointed brackets indicate that you replace these words and characters with appropriate entries.

External Backup Tools: SAP DB	5
Performing a Backup with External Backup Tools.....	5
Restore with External Backup Tools.....	6
Determine and Display External Backup ID (DBMCLI).....	7
Determine and Display External Backup ID (DBMGUI).....	8
Performing a Recovery with External Backup Tools (DBMCLI).....	8
Performing a Recovery with External Backup Tools (DBMGUI).....	10
Configuring the TSM Connection.....	11
Availability of the TSM Connection	11
Backup Medium (TSM).....	12
Setting Environment Variables ADINT and ADA_OPT	12
Performing Parallel Backups (TSM).....	13
Configuring the Backint for Oracle Connection.....	13
Adapter Program	14
Availability of the Backint for Oracle Connection	15
Backup Medium (Backint for Oracle)	15
Configuration File (Adapter Program)	16
Example Configuration File (Adapter Program).....	17
Parallel Backups (Backint for Oracle)	18
Configuring the Backint for SAP DB Connection	19
Availability of the Backint for SAP DB Connection.....	19
Backup Medium (Backint for SAP DB).....	20
Setting Environment Variable BSI_ENV	20
Configuration File (Backint for SAP DB)	21
Example Configuration File (Backint for SAP DB).....	22
Parallel Backups (Backint for SAP DB).....	22
Configuring the NetWorker Connection	23
Availability of the NetWorker Connection.....	23
Backup Medium (NetWorker).....	24
Setting Environment Variable NSR_ENV.....	25
Configuration File (NetWorker).....	25
Example Configuration File (NetWorker).....	28
Parallel Backups (NetWorker).....	29
Terms and Procedures	30
Media Name	30
External Backup ID.....	31
Setting Environment Variables	31



External Backup Tools: SAP DB

You can back up and recover SAP DB databases by using external backup tools.



For general information on the SAP DB database system, see the documentation [The SAP DB Database System](#).

This description of how to use the external backup tools applies for the SAP DB versions specified in the relevant sections. It does not matter what kind of database instance ([SAP DB OLTP](#), [liveCache](#), [SAP DB Document Server](#), [SAP DB OLAP](#), [SAP DB E-Catalog](#)) you use. For more information about which database instance types are supported by which versions of SAP DB, see [SAP DB Versions and Database Instance Types](#).

There may be differences between UNIX and Microsoft Windows-based [operating system platforms](#). For simplicity, the abbreviations UNIX and Windows are used.

Using External Backup Tools

- [Performing a Backup with External Backup Tools \[Page 5\]](#)
- [Performing a Recovery with External Backup Tools \[Page 6\]](#)

Configuring External Backup Tools

- [Configuring the TSM Connection \[Page 11\]](#)
- [Configuring the Backint for Oracle Connection \[Page 13\]](#)
- [Configuring the Backint for SAP DB Connection \[Page 19\]](#)
- [Configuring the NetWorker Connection \[Page 23\]](#)

Additional Information

- [Terms and Procedures \[Page 30\]](#)



Performing a Backup with External Backup Tools

You can use external backup tools to save to tapes and succeeding tapes. The [Database Manager](#) currently supports the following backup tools:

- TSM
- Backint for Oracle
- Backint for SAP DB
- NetWorker

Using the Backup Tools

You start the backup process directly from the Database Manager. Due to the naming conventions for backup media ([media name \[Page 30\]](#)), the program recognizes the external backup tool and starts it. The pipes for transferring the backup data are implicitly created by the Database Manager or the database instance during the backup process. They must therefore not already exist.

Prerequisites

The database instance must be in operational mode ADMIN or ONLINE. You have created the media in accordance with the naming conventions for external backup media. You have configured the relevant backup tool.

Backup tool	See:
TSM	Configuring the TSM Connection [Page 11]
Backint for Oracle	Configuring the Backint for Oracle Connection [Page 13]
Backint for SAP DB	Configuring the Backint for SAP DB Connection [Page 19]
NetWorker	Configuring the NetWorker Connection [Page 23]

You have inserted the required media.

Procedure

Follow the procedure described in the documentation for the Database Manager for backups with external backup tools.

Database Manager GUI: SAP DB 7.4, [Backup Processes](#) section.

Database Manager CLI: SAP DB 7.4, [Commands for Backing Up and Archiving](#) section.



Backing up with TSM:

```
dbmcli -u dbm,dbm -uUTL -d mydb backup_start ADSMData data
```

The information relevant to the backup appears after the keyword

```
backup_start:
```

```
Name of the backup medium: ADSMData
```

```
Type of backup: data (complete data backup)
```



Restore with External Backup Tools

You can perform backups using external backup tools ([Backup with External Backup Tools \[Page 5\]](#)). Restoring with external backup tools is supported by the [Database Manager](#) for the following backup tools:

- ADSM/TSM
- Backint for Oracle
- Backint for SAP DB
- NetWorker

Use of Backup Tools

You start the restore process directly from the Database Manager. Due to the naming conventions for backup media ([media name \[Page 30\]](#)), the program recognizes the external backup tool and starts it.

Procedure

- If you use the Database Manager CLI for the restore, you must [determine and display the external backup ID \(DBMCLI\) \[Page 7\]](#).
- The Database Manager GUI automatically determines all of the required information for the restore.

The Database Manager identifies the backup to be restored using the [external backup ID \[Page 31\]](#).



The number of media in a group of parallel media must be the same as the number that was used for the creation of the backup.

Start the restore of the database instance.

- If you are using the Database Manager CLI, follow the procedure in [Restore with External Backup Tools \(DBMCLI\) \[Page 8\]](#).
- If you are using the Database Manager GUI, follow the procedure in [Restore with External Backup Tools \(DBMGUI\) \[Page 10\]](#).



Determine and Display External Backup ID (DBMCLI)

When you [restore with external backup tools \[Page 6\]](#), the [Database Manager](#) identifies the backup to be restored using the [External Backup IDs \[Page 31\]](#).

Prerequisites

You have configured the desired backup tool.

Procedure

You can determine and display the information about the backups known to the backup tool, and in particular about the external backup IDs, using the following commands in an interactive Database Manager CLI session:

1. Querying the External Backup IDs

DBMCLI Command:

```
backup_ext_ids_get <medium> [<database_name> [<server_node>]]
```

<medium>: Name of the backup medium

<database_name>: Name of the database instance of which the backup was created

<server_node>: Name of the server on which the backups were created

2. Reading External Backup IDs

DBMCLI Command: **backup_ext_ids_get**

The external backup IDs, the type of backup and the date and time of the backup are displayed for every backup still known to the backup tool.

If a backup is still known to the backup tool but can no longer be used for a restore, the word UNAVAILABLE appears instead of AVAILABLE in the appropriate line.

If the response packet from the Database Manager does not contain all of the relevant information, the keyword CONTINUE appears in the response. If this is the case, continue with **step 3**.

If the first response packet from the Database Manager does contain all of the relevant information, the keyword END appears in the response instead of CONTINUE. If this is the case, continue with **step 4**.

3. Scrolling in the External Backup IDs

Display all further parts of the response until all of the information from the Database Manager has been transferred or you have been able to determine the external backup IDs of the desired backups.

DBMCLI Command: **backup_ext_ids_listnext**

If the first response packet from the Database Manager contains all of the available information, the keyword END appears in the response. Continue with **step 4**.

4. Release of the Working Memory, that was used by the external backup IDs

DBMCLI commando: **backup_ext_ids_forget**

If you run this command, the Database Manager will no longer have any information

about the external backup IDs. If you want to determine the external backup IDs after you have released the working memory, you must query the external backup IDs again and then read them.

Or **End the DBMCLI:**

DBMCLI command: `exit`

See also:

Database Manager CLI: SAP DB 7.4, [Commands for Backup IDs](#) section.



Determine and Display External Backup ID (DBMGUI)

When you [restore with external backup tools \[Page 6\]](#), the [Database Manager](#) identifies the backup to be restored using the [External Backup IDs \[Page 31\]](#).

Prerequisites

You have configured the desired backup tool.

Procedure

- You can determine and display the information about the backups known to the backup tool, and in particular about the external backup IDs, using the Database Manager GUI: *Database Manager GUI: SAP DB 7.4, [Display Backup History](#) section.*
- The information about the backups known to the backup tool, and in particular the external backup IDs, are displayed by the DBMGUI during a restore. *Database Manager GUI: SAP DB 7.4, sections [Restoring the Last Complete Data Backup](#) / [Restoring a Backup from the Backup History](#) / [Restoring Without a Backup History](#)*



Performing a Recovery with External Backup Tools (DBMCLI)

If you use [external backup tools for recovery \[Page 6\]](#), you have to specify the [external backup IDs \[Page 31\]](#) of the relevant backups.

Prerequisites

The operational state of the database instance is ADMIN. You have configured the relevant backup tool.

Backup tool	See:
TSM	Configuring the TSM Connection [Page 11]
Backint for Oracle	Configuring the Backint for Oracle Connection [Page 13]
Backint for SAP DB	Configuring the Backint for SAP DB Connection [Page 19]
NetWorker	Configuring the NetWorker Connection [Page 23]

You have determined the necessary external backup IDs (see [Determining and Displaying the External Backup ID \(DBMCLI\) \[Page 7\]](#) or [Determining and Displaying the External Backup ID \(DBMGUI\) \[Page 8\]](#)).

You have inserted the required [backup medium](#).

Procedure

You can perform a recovery with an interactive session of the [Database Manager CLI](#), or non-interactively.

Recovery Commands for an Interactive DBMCLI Session

You can recover a [data backup](#) (complete or incremental) and the first [log backup](#) interactively by using the following DBMCLI commands:

recover_start <medium> <type> ExternalBackupID <external_backup_ID>

- <medium>: Backup medium (see [Media Name \[Page 30\]](#)), from where you want to import the backup (if necessary, enter a media group here)
- <type>: Type of backup
 data: Complete data backup
 pages: Incremental data backup
 log: Log backup
- <external_backup_ID>: External backup ID that is used to identify the backup to the external backup tool
 If the external backup ID contains blank characters, you have to enter the external backup ID in quotation marks:
 "<external_backup_ID>"
 For parallel backups, all the external backup IDs of each backup part have to be separated by a comma and transferred as a whole list set in quotation marks:
 "<external_backup_ID1>, <external_backup_ID2>, ..., <external_backup_IDn>"

If it is necessary to import more than one **log backup**, the second and all subsequent log backups can be imported interactively by using the following DBMCLI commands:

recover_replace <medium> ExternalBackupID <external_backup_ID>

If the external backup ID contains blank characters, you have to enter the it in quotation marks:

"<external_backup_ID>"



In most cases you have to import more than one log backup. For this reason, you must always perform log backups in interactive DBMCLI sessions so that you can react to the requirements of the database kernel (additional log backups required). To import all the log backups, you use the command **recover_start**, and then you have to use the command **recover_replace**.

Example of a Recovery Command for a Non-Interactive DBMCLI Session

Recovery with NetWorker (non-interactive):



```
dbmcli -u dbm,dbm -uUTL -d mydb recover_start NSRPages pages
ExternalBackupID "NST 994245367 P47579"
```

The relevant information for the recovery appears after the keyword **recover_start**:

Name of backup medium: NSRPages

Type of backup: pages (incremental backup)

External backup ID: NST 994245367 P47579



For non-interactive DBMCLI sessions, note the rules of the relevant shell regarding quotation marks. It is important that the quotation marks are communicated to the Database Manager.

See also:

Database Manager CLI: SAP DB 7.4, section [Commands for Recovery](#)

Result

The relevant backup ID is communicated to the Database Manager, and the recovery is started.



Performing a Recovery with External Backup Tools (DBMGUI)

When you use [external backup tools for recovery \[Page 6\]](#), the [external backup IDs \[Page 31\]](#) are automatically determined by the [Database Manager GUI](#), displayed so that the user can check them, and used by the Database Manager GUI for the recovery. The user does not have to explicitly determine or specify the external backup IDs because the Database Manager GUI determines the necessary information.

If you want to display the external backup IDs for information purposes, you have the following options:

- [Determining and Displaying External Backup IDs \(DBMCLI\) \[Page 7\]](#)
- [Determining and Displaying External Backup IDs \(DBMGUI\) \[Page 8\]](#)

Prerequisites

The operational state of the database instance is ADMIN. You have configured the relevant backup tool.

Backup tool	See:
TSM	Configuring the TSM Connection [Page 11]
Backint for Oracle	Configuring the Backint for Oracle Connection [Page 13]
Backint for SAP DB	Configuring the Backint for SAP DB Connection [Page 19]
NetWorker	Configuring the NetWorker Connection [Page 23]

You have inserted the required [backup medium](#).

Procedure

Start the recovery. Proceed as described in the documentation about the Database Manager GUI.

Database Manager GUI: SAP DB 7.4, section [Recovering the Last Complete Data Backup](#), or [Recovering a Backup from the Backup History](#), or [Recovering Without a Backup History](#)

Result

The selected backups are restored with the help of the external backup tool.



Configuring the TSM Connection

Prerequisites

The [TSM connection \[Page 11\]](#) must be available.

Procedure

You can perform the configuration for the SAP DB database system as follows:

1. Create an appropriate [backup medium \[Page 12\]](#) with the Database Manager.
2. Set the environment variables ADINT and ADA_OPT (see [Setting Environment Variables ADINT and ADA_OPT \[Page 12\]](#)).
3. If you want to perform parallel backups, note the information in the [Parallel Backups \[Page 13\]](#) section.
4. Test the following procedures:
[Performing a Backup with External Backup Tools \[Page 5\]](#)
[Performing a Recovery with External Backup Tools \[Page 6\]](#)



Availability of the TSM Connection

The connection to the backup tool TSM from IBM/Tivoli is available as of the following SAP DB versions for the specified SAP DB tools:

SAP DB version	Build	SAP DB Tools for TSM Backup	SAP DB Tools for TSM Recovery
7.2.03	007	DBMCLI, DBMGUI	DBMCLI
7.2.04	000	DBMCLI, DBMGUI	DBMCLI
7.2.05	000	DBMCLI, DBMGUI	DBMCLI
7.3.00	000	DBMCLI, DBMGUI	DBMCLI
	015	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.3.32	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.4.02	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

See also:

[Configuring the TSM Connection \[Page 11\]](#)

The SAP DB Database System, sections [Operating System Platforms](#), and [SAP DB Versions and Database Instance Types](#).



Backup Medium (TSM)

If you want to perform a backup or a recovery with the external backup tool TSM, you must define the appropriate [backup media](#) with the [Database Manager](#).

Procedure

To create the backup medium, follow the procedure described in the Database Manager documentation.

- *Database Manager GUI*: SAP DB 7.4, [Managing the Backup Media](#) section.
- *Database Manager CLI*: SAP DB 7.4, [Commands for Backup Media](#) section.

The [media name \[Page 30\]](#) must begin with the character string **ADSM**.



Definition of a pipe as a medium for an incremental data backup with a DBMCLI command (Microsoft Windows):

```
dbmcli -d <database_name> -u <userid>,<password> medium_put
ADSM123 \\.\pipe\EXAMPLE pipe pages
```

The backup medium must be a pipe and must not have any capacity limits.

The pipes used must not exist. Specify the absolute name of a pipe.

- Microsoft Windows: Pipe names must be in the following form:
\\.\pipe**<pipe_name>**
- UNIX: There are no particular naming conventions to follow for pipe names.

You can perform [parallel backups \[Page 13\]](#) using multiple pipes.

See also:

[Configuring the TSM Connection \[Page 11\]](#)



Setting Environment Variables ADINT and ADA_OPT

One step in the [configuration of the TSM connection \[Page 11\]](#) is that you must set the environment variables **ADINT** and **ADA_OPT**.

Environment Variable	
ADINT	Specifies the directory in which the program <code>adint2</code> (UNIX) or <code>adint2.exe</code> (Windows) is stored. This directory must be specified as an absolute path, that is, without a closing / or \.
ADA_OPT	Absolute name of the <code>adint2</code> configuration file. You will find an example configuration file <code>initSID.ut1</code> in the directory of the <code>adint2</code> program.

Procedure

Follow the procedure described in [Setting Environment Variables \[Page 31\]](#).



Performing Parallel Backups (TSM)

Prerequisites

You have configured TSM according to the details in the section [Configuring the TSM Connection \[Page 11\]](#).

The following table informs you for which SAP DB versions you can use TSM to perform a parallel backup or a recovery.

SAP DB version	Build	SAP DB tools for parallel TSM backup	SAP DB tools for parallel TSM recovery
7.2.05	017	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.3.00	021	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.02	003	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

See also:

The SAP DB Database System, sections [Operating System Platforms](#), [SAP DB Versions and Database Instance Types](#)

Using the [Database Manager](#), you have to configure a media group whose members correspond to the conventions described in the section [Backup Medium \[Page 12\]](#). In particular, each [media group name \[Page 30\]](#) must have the prefix **ADSM**.

Parallel backups can be performed for data backups (complete and incremental) only.

Procedure

If you want to perform a parallel backup or recovery, proceed as described in the following documentation:

- *Database Manager GUI: SAP DB 7.4*, section [Backing Up on a Group of Parallel Backup Media](#) or [Recovering Data](#)
- *Database Manager CLI: SAP DB 7.4*, section [Commands for Backing Up and Archiving](#) or [Commands for Recovery](#)



Configuring the Backint for Oracle Connection

To enable you to connect Backint for Oracle to SAP DB, an adapter program is delivered with the SAP DB software, which meets the Backint for SAP DB specification. This program uses Backint for Oracle to backup the data with the chosen backup tool.

The interface program Backint for Oracle can backup any files in the file system, regardless of whether the Oracle database system is installed on the server or not. This attribute must be assured by the vendor of the relevant Backint for Oracle program.

Prerequisites

Find out about the way in which the Backint for SAP DB [adapter program \[Page 14\]](#) and the interface program Backint for Oracle work.
[Availability of Backint for Oracle Connections \[Page 15\]](#)

Procedure

You can perform the configuration for the SAP DB database system as follows:

1. Set up a Backint for SAP DB connection ([Configuring the Backint for SAP DB Connection \[Page 19\]](#)). During the setup of the Backint for SAP DB connection, an appropriate [backup medium \[Page 15\]](#) is created with the Database Manager. This step is necessary for the Database Manager to recognize where it can find the Backint for SAP DB adapter program and how the Database Manager should run this adapter program.
2. Create a [configuration file \(adapter program\) \[Page 16\]](#) for the Backint for SAP DB adapter program (see also: [Example Configuration File \(Adapter Program\) \[Page 17\]](#)). You must enter the name of this configuration file in the [configuration file \(Backint for SAP DB\) \[Page 21\]](#) for the Backint for SAP DB connection.
3. Install and configure the interface program Backint for Oracle delivered by the backup tool vendor in accordance with the vendor's instructions. If Backint for Oracle must be configured using a parameter file, you must specify the name of the parameter file in the configuration file for the Backint for SAP DB adapter program (see step 2).
4. If you want to perform parallel backups, note the information in the [parallel backups \[Page 18\]](#) section.
5. Test the following procedures:
[Backup with External Backup Tools \[Page 5\]](#)
[Restore with External Backup Tools \[Page 6\]](#)



Adapter Program

To enable you to connect Backint for Oracle to SAP DB, an adapter program is delivered with the SAP DB software, which meets the Backint for SAP DB specification.

The adapter program works as follows during a **backup**:

1. The backup data of the database system is received using one or more pipes.
2. This data is saved in temporary files of configurable size.
3. The temporary files are saved by the adapter program using Backint for Oracle.
4. The temporary files are deleted.
5. If necessary, this procedure is repeated from the second step as long as is necessary to process all of the backup data.

If you are performing a backup or a restore using multiple pipes, you can configure the adapter program so that new temporary files are created at the same time as temporary files that have already been created are saved using Backint for Oracle.

Administration information is recorded in a history file that is also saved using Backint for Oracle after the backup.

The adapter program works as follows during a **restore**:

1. The information in the history file is evaluated. If this history file no longer exists, the last version of the history file must be manually restored using Backint for Oracle.
2. The required temporary files are restored in the correct order using Backint for Oracle.
3. The data is transferred to the database system using one or more pipes.

See also:

[Configuring the Backint for SAP DB Connection \[Page 13\]](#)



Availability of the Backint for Oracle Connection

The connection to the backup tool Backint for Oracle is available as of the following SAP DB versions for the specified SAP DB tools:

SAP DB Version	Build	SAP DB Tools for Backint Backups	SAP DB Tools for Backint Restores
7.2.05	008	DBMCLI, DBMGUI	DBMCLI
7.3.00	015	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.3.32	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.4.02	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

See also:

[Configuring the Backint for Oracle Connection \[Page 13\]](#)

User Manual: SAP DB, sections [Operating System Platforms](#), and [SAP DB Versions and Database Instance Types](#).



Backup Medium (Backint for Oracle)

If you want to perform backups or restores with the external backup tool Backint for Oracle, you must define the appropriate [backup media](#) with the [Database Manager](#).

Procedure

To create the backup medium, follow the procedure described in the Database Manager documentation.

- *Database Manager GUI:* SAP DB 7.4, [Managing the Backup Media](#) section.
- *Database Manager CLI:* SAP DB 7.4, [Commands for Backup Media](#) section.

The [media name \[Page 30\]](#) must begin with the character string **BACK**.



Definition of a pipe as a medium for an incremental data backup with a DBMCLI command (Microsoft Windows):

```
dbmcli -d <database_name> -u <user_id>,<password>
medium_put BACK123 \\.\pipe\EXAMPLE pipe pages
```

The backup medium must be a pipe and must not have any capacity limits.

The name of the pipe must be specified as an absolute path. The pipes used must not exist.

- Microsoft Windows: Pipe names must be in the following form:
\\.\pipe**<pipe_name>**
- UNIX: There are no particular naming conventions to follow for pipe names.

You can perform [parallel backups \[Page 18\]](#) using multiple pipes.

See also:

[Configuring the Backint for Oracle Connection \[Page 13\]](#)



Configuration File (Adapter Program)

To be able to use the backup tool Backint for Oracle, you must, as a step of the [Configuring the Backint for Oracle Connection \[Page 13\]](#), create a configuration file for the Backint for SAP DB [adapter program \[Page 14\]](#). This configuration file tells the adapter program, among other things, where it should create the necessary temporary files and where it can find the interface program Backint for Oracle. The name of this configuration file must be stored in the [configuration file \[Page 21\]](#) for the Backint for SAP DB connection (Parameter `PARAMETERFILE <value>`).

Procedure

You can define a parameter in the format `<key_string> <value_string>` in each line of the configuration file.

- `<key_string>`: A keyword or keywords must be specified at the beginning of each line. Lines without one of the permissible keywords are ignored.
- `<value_string>`: Value(s) of the parameter.

If you want to avoid a certain parameter being set by the configuration file, you must completely remove the corresponding line with the format `<key_string> <value_string>` from the configuration file.

You can use the following keywords to define parameters:

Keyword(s)	Value(s)
STAGING AREA:	Absolute path and size of a temporary file STAGING AREA: <code><absolute_path> <size> [KB MB GB]</code> If you do not specify a size unit, the size is configured in bytes. Up to 256 temporary files of this type can be defined. Exactly one temporary file is used for each pipe used.
FILES PER BACKINT CALL:	Maximum number of temporary files that are to be processed by Backint for Oracle concurrently. In this way, temporary files can be created at the same time as other temporary files are backed up.
BACKINT:	Absolute name of the interface program Backint for Oracle
PARAMETERFILE OF BACKINT:	Absolute name of a parameter file for the interface program Backint for Oracle The line <code>PARAMETERFILE OF BACKINT: <value_string></code> should not appear in the configuration file, if no parameter file is required for Backint for Oracle. The name of the parameter file is transferred to Backint for Oracle as a parameter. It is therefore possible to configure the Backint for Oracle program in accordance with the specifications in this parameter file. The description of a parameter file of this type is provided by the backup tool vendor.

HISTORY FILE:	<p>Absolute name of the history file</p> <p>The adapter program stores the information required for restores in the history file.</p> <p>If more than one SAP DB version is backed up on one server, a different history file must be used for each database system. If the history file is damaged, this file must be restored manually with the help of the Backint for Oracle program. You should ensure that you are familiar with Backint for Oracle and handling of your backup tool in case this is necessary.</p>
INPUTFILE FOR BACKINT: OUTPUT FILE FOR BACKINT ERRORFILE FOR BACKINT:	<p>Specifies which files are used for standard input, standard output and error output for the Backint for Oracle processes to be started</p> <p>These files must be different from the files configured for the Backint for SAP DB connections (see INPUT, OUTPUT, ERROROUTPUT in Configuration File (Backint for SAP DB) [Page 21])</p>
MAXIMAL DELAY OF BACKINT CALL:	<p>Maximum time in seconds that Backint for Oracle should wait after the creation of a temporary file through a call of Backint for Oracle, until the complete number of temporary files has been created, as specified in the line FILES PER BACKINT CALL: <value_string>.</p> <p>This specification helps to avoid deadlocks that can occur in exceptional situations. The length of time must be large enough so that during normal backup operation, the configured number of temporary files can be saved at the same time using Backint for Oracle. On the other hand, the time must not be too large, so that the end of the backup is not extended too far due to unfavorable configurations.</p>
OMIT LAST DIRECTORY DELIMITER ON RESTORE:	<p>Specifies whether or not the adapter program should ignore the closing slash (/ or \) of an absolute directory name for Backint for Oracle.</p> <p>NO (Default): The slash is not ignored.</p> <p>YES: The slash is ignored.</p> <p>Use this option to avoid problems with Backint for Oracle implementations that do not expect a closing slash (/ or \) at the end of a directory name.</p> <p>This specification is supported as of the following SAP DB versions: 7.2.05.016, 7.3.00.021, 7.4.02.002, 7.4.03.000</p>

See also:

[Example Configuration File \[Page 17\]](#)



Example Configuration File (Adapter Program)

The [configuration file \[Page 16\]](#) for the [adapter program \[Page 14\]](#) that is required for a Backint for Oracle connection can be explained using the following example.

Example

```

STAGING AREA:          D:\TEMP\STAGE1 1 GB
STAGING AREA:          E:\TEMP\STAGE2 1024 MG
STAGING AREA:          F:\TEMP\STAGE3 1048576 KB
STAGING AREA:          G:\TEMP\STAGE4 1073741824

FILES PER BACKINT CALL: 2

BACKINT:                C:\BackupTool\BIN\backint.exe
PARAMETERFILE OF BACKINT: C:\BackupTool\CONF\backintparam.utl

HISTORY FILE:           C:\SAPDB\BackintHistory

```

INPUTFILE FOR BACKINT: C:\TEMP\backint4Oracle.in
 OUTPUTFILE FOR BACKINT: C:\TEMP\backint4Oracle.out
 ERRORFILE FOR BACKINT: C:\TEMP\backint4Oracle.err
 MAXIMAL DELAY OF BACKINT CALL: 30

Explanation

Keyword(s)	Value(s)	Explanation
STAGING AREA:	D:\TEMP\STAGE1 1 GB E:\TEMP\STAGE2 1024 MG F:\TEMP\STAGE3 1048576 KB G:\TEMP\STAGE4 1073741824	The adapter program can backup or restore a maximum of four pipes at the same time. The temporary files created in doing this can reach a size of a Gigabyte, as long as the end of the pipe is not reached.
FILES PER BACKINT CALL:	2	If two of the four temporary files are completely created, these are backed up with the help of a call of the interface program Backint for Oracle.
BACKINT:	C:\Backuptool\BIN\backint.exe	The name of the interface program Backint for Oracle is: C:\Backuptool\BIN\backint.exe
PARAMETERFILE OF BACKINT:	C:\BackupTool\CONF\backintparam.utl	The Backint for Oracle program uses the parameter file C:\BackupTool\CONF\backintparam.utl.
HISTORY FILE:	C:\SAPDB\BackintHistory	The adapter program stores its information in the history file C:\SAPDB\BackintHistory at the end of every backup and stores this file with an additional call of Backint for Oracle.
INPUTFILE FOR BACKINT: OUTPUTFILE FOR BACKINT: ERRORFILE FOR BACKINT:	C:\TEMP\backint4Oracle.in C:\TEMP\backint4Oracle.out C:\TEMP\backint4Oracle.err	Standard input for Backint for Oracle: C:\TEMP\backint4Oracle.in Standard output for Backint for Oracle: C:\TEMP\backint4Oracle.out Standard error output for Backint for Oracle: C:\TEMP\backint4Oracle.err
MAXIMAL DELAY OF BACKINT CALL:	30	If the temporary files are created at different speeds and one temporary file is already complete, the adapter program waits a maximum of 30 seconds for another of the temporary files to be completely created. If none of the other files is created within 30 seconds, the temporary file that already exists is backed up using Backint for Oracle.



Parallel Backups (Backint for Oracle)

Prerequisites

You have configured the Backint for Oracle connection in accordance with the specifications in [Configuring the Backint for Oracle Connection \[Page 13\]](#).

You must configure a media group with the [Database Manager](#), the individual members of which conform to the conventions described in [backup medium \[Page 15\]](#). In particular, every [media group name \[Page 30\]](#) must begin with `BACK`.

Parallel backups are only possible for data backups (complete and incremental).

Procedure

If you want to perform a parallel backup or restore, follow the procedure described in the following documentation:

- *Database Manager GUI: SAP DB 7.4*, sections [Saving to a Group of Parallel Backup Media](#) and [Recovery](#).
- *Database Manager CLI: SAP DB 7.4*, sections [Commands for Backups](#) and [Commands for Restoring](#).



Configuring the Backint for SAP DB Connection

Prerequisites

[Availability of the Backint for SAP DB Connection \[Page 19\]](#)

Procedure

You can perform the configuration for the SAP DB database system as follows:

1. Create an appropriate [backup medium \[Page 20\]](#) with the Database Manager.
2. Set the environment variable `BSI_ENV` ([Setting the Environment Variable BSI_ENV \[Page 20\]](#)).
3. Create a [configuration file \[Page 21\]](#) (see also: [Example Configuration File \[Page 22\]](#)).
4. If you want to perform parallel backups, note the information in the [parallel backups \[Page 22\]](#) section.
5. Test the following procedures:
[Backup with External Backup Tools \[Page 5\]](#)
[Restore with External Backup Tools \[Page 6\]](#)



Availability of the Backint for SAP DB Connection

The connection to the backup tool Backint for SAP DB is available as of the following SAP DB versions for the specified SAP DB tools:

SAP DB Version	Build	SAP DB Tools for Backint Backups	SAP DB Tools for Backint Restores
7.2.05	008	DBMCLI, DBMGUI	DBMCLI
7.3.00	015	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.3.32	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.4.02	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

See also:

[Configuring the Backint for SAP DB Connection \[Page 19\]](#)

User Manual: SAP DB, sections [Operating System Platforms](#), and [SAP DB Versions and Database Instance Types](#).



Backup Medium (Backint for SAP DB)

If you want to perform backups or restores with the external backup tool Backint for SAP DB, you must define the appropriate [backup media](#) with the [Database Manager](#).

Procedure

To create the backup medium, follow the procedure described in the Database Manager documentation.

- *Database Manager GUI: SAP DB 7.4*, [Managing the Backup Media](#) section.
- *Database Manager CLI: SAP DB 7.4*, [Commands for Backup Media](#) section.

The [media name \[Page 30\]](#) must begin with the character string **BACK**.



Definition of a pipe as a medium for an incremental data backup with a DBMCLI command (Microsoft Windows):

```
dbmcli -d <database_name> -u <user_id>,<password>
medium_put BACK123 \\.\pipe\Example pipe pages
```

The backup medium must be a pipe and must not have any capacity limits.

The name of the pipe must be specified as an absolute path. The pipes used must not exist.

- Microsoft Windows: Pipe names must be in the following form:
\\.\pipe**<pipe_name>**
- UNIX: There are no particular naming conventions to follow for pipe names.

You can perform [parallel backups \[Page 22\]](#) using multiple pipes.

See also:

[Configuring the Backint for SAP DB Connection \[Page 19\]](#)



Setting Environment Variable BSI_ENV

One step in the [configuration of Backint for SAP DB Connections \[Page 19\]](#) is that you must set the environment variable **BSI_ENV** so that it contains the absolute path of the [configuration file \[Page 21\]](#).

If the environment variable **BSI_ENV** is not set, the system will attempt to use the file specified in the table as the configuration file:

Operating System	File
UNIX	< Run Directory >/bsi.env

Microsoft Windows

<Run directory>\bsi.env

Procedure

Follow the procedure described in [Setting environment variables \[Page 31\]](#).



Configuration File (Backint for SAP DB)

To be able to use the backup tool Backint for SAP DB, you must create a configuration file as a step of the [Configuring the Backint for SAP DB Connection \[Page 19\]](#).

Procedure

You can define a parameter in the format <key_word> <value> in each line of the configuration file.

- <key_word>: A key word must be specified at the beginning of each line. Lines without one of the permissible keywords are ignored.
- <value>: Value of the parameter. If this value contains a blank character or another space character, place the value in quotation marks.

If you want to avoid a certain parameter being set by the configuration file, you must completely remove the corresponding line with the format <key_word> <value> from the configuration file.

You can use the following keywords to define parameters:

Keyword	Value
BACKINT	Absolute name of the Backint for SAP DB program
INPUT OUTPUT ERROROUTPUT	Absolute paths of files The Database Manager creates these files temporarily and uses them for standard input, output, and error output for Backint for SAP DB.
PARAMETERFILE	Absolute path of a parameter file If PARAMETERFILE <value> is specified, the path specified in <value> is sent to Backint for SAP DB every time the parameter is called. In this way, you can configure the Backint for SAP DB program. The format of this parameter file depends on which version of Backint for SAP DB you are using, and will be described by its vendor.
TIMEOUT_SUCCESS TIMEOUT_FAILURE	Specifies how many seconds after starting the Database Manager waits for Backint for SAP DB to terminate in the case of success and of failure. Default values: TIMEOUT_SUCCESS 300, TIMEOUT_FAILURE 300
ORIGINAL_RUNDIRE CTORY	Absolute path of the run directory of the source database You only need to specify the parameter ORIGINAL_RUNDIRECTORY <value> in the case of a database migration (Restore of a database in a new working directory). The prerequisite for the migration from one server to another is that the version of Backint for SAP DB that you are using can make backups from the source server available on the target server. This value is case sensitive.

See also:

[Example Configuration File \[Page 22\]](#)



Example Configuration File (Backint for SAP DB)

The [configuration file \[Page 21\]](#) for a Backint for SAP DB connection can be explained using the following example.

Example

```
BACKINT                C:\Backuptool\backint.exe
INPUT                  C:\TEMP\backint4SAPDB.in
OUTPUT                 C:\TEMP\backint4SAPDB.out
ERROROUTPUT           C:\TEMP\backint4SAPDB.err
PARAMETERFILE         C:\SAPDB\WRK\TST\backint.par
TIMEOUT_SUCCESS       600
TIMEOUT_FAILURE       300
ORIGINAL_RUNDIRECTORY C:\SAPDB\wrk\Pl
```

Explanation

Keyword	Value	Explanation
BACKINT	C:\Backuptool\backint.exe	The Database Manager runs the program C:\Backuptool\backint.exe for backups and restores with the Backint for SAP DB.
INPUT OUTPUT ERROROUTPUT	C:\TEMP\backint4SAPDB.in C:\TEMP\backint4SAPDB.out C:\TEMP\backint4SAPDB.err	Standard input: C:\TEMP\backint4SAPDB.in Standard output: C:\TEMP\backint4SAPDB.out Standard error output: C:\TEMP\backint4SAPDB.err
PARAMETERFILE	C:\SAPDB\WRK\TST\backint.par	Backint for SAP DB uses the parameter file C:\SAPDB\WRK\TST\backint.par.
TIMEOUT_SUCCESS TIMEOUT_FAILURE	600 300	In the case of success, the Database Manager waits a maximum of ten minutes for Backint for SAP DB to terminate. In the case of error, the Database Manager waits five minutes.
ORIGINAL_RUNDIRECTORY	C:\SAPDB\wrk\Pl	If a database different from the current database is to be restored, the run directory of the database to be restored must have been: C:\SAPDB\wrk\Pl.



Parallel Backups (Backint for SAP DB)

Prerequisites

You have configured Backint for SAP DB in accordance with the specifications in [Configuration of Backint for SAP DB Connection \[Page 19\]](#).

You must configure a media group with the [Database Manager](#), the individual members of which conform to the conventions described in [backup medium \[Page 20\]](#). In particular, every [media group name \[Page 30\]](#) must begin with **BACK**.

Parallel backups are only possible for data backups (complete and incremental).

Procedure

If you want to perform a parallel backup or restore, follow the procedure described in the following documentation:

- *Database Manager GUI: SAP DB 7.4*, sections [Saving to a Group of Parallel Backup Media](#) and [Recovery](#).
- *Database Manager CLII: SAP DB 7.4*, sections [Commands for Backups](#) and [Commands for Restoring](#).



Configuring the NetWorker Connection

Prerequisites

[Availability of the NetWorker Connection \[Page 23\]](#)

Procedure

You can perform the configuration for the SAP DB database system as follows:

1. Create an appropriate [backup medium \[Page 24\]](#) with the Database Manager.
2. Set the environment variable NSR_ENV ([Setting the Environment Variable NSR_ENV \[Page 25\]](#)).
3. Create a [configuration file \[Page 25\]](#) (see also: [Example Configuration File \[Page 28\]](#)).
4. If you want to perform parallel backups, note the information in the [parallel backups \[Page 29\]](#) section.
5. Test the following procedures:
[Backup with External Backup Tools \[Page 5\]](#)
[Restore with External Backup Tools \[Page 6\]](#)



Availability of the NetWorker Connection

The connection to the backup tool NetWorker from the company Legato is available as of the following SAP DB versions for the specified SAP DB tools:

SAP DB Version	Build	SAP DB Tools for NetWorker Backups	SAP DB Tools for NetWorker Restores
7.2.04	015	DBMCLI, DBMGUI	DBMCLI
7.2.05	001	DBMCLI, DBMGUI	DBMCLI
7.3.00	005	DBMCLI, DBMGUI	DBMCLI
	015	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.3.32	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.4.02	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

The following NetWorker versions are the minimum required:

Operating System	NetWorker Version
UNIX	5.5
Microsoft Windows	5.7

See also:

[Configuration of the NetWorker Connection \[Page 23\]](#)

User Manual: SAP DB, sections [Operating System Platforms](#), and [SAP DB Versions and Database Instance Types](#).



Backup Medium (NetWorker)

If you want to perform backups or restores with the external backup tool NetWorker, you must define the appropriate [backup media](#) with the [Database Manager](#).

Procedure

To create the backup medium, follow the procedure described in the Database Manager documentation.

- *Database Manager GUI: SAP DB 7.4*, [Managing the Backup Media](#) section.
- *Database Manager CLI: SAP DB 7.4*, [Commands for Backup Media](#) section.

The [media name \[Page 30\]](#) must begin with the character string **NSR**.



Definition of a pipe as a medium for an incremental data backup with a DBMCLI command (Microsoft Windows):

```
dbmcli -d <database_name> -u <userid>,<password> medium_put
NSR123 \\.\pipe\Example pipe pages
```

The backup medium must be a pipe and must not have any capacity limits.

The name of the pipe must be specified as an absolute path. The pipes used must not exist.

- Microsoft Windows: Pipe names must be in the following form:
\\.\pipe\<pipe_name>
- UNIX: There are no particular naming conventions to follow for pipe names.

The absolute name of the pipe must be identical at backups and restores. Note that file or directory paths that are specified as links are resolved by the backup tool NetWorker.



On Server A, a backup is performed using /tmp/nsr_pipe. The directory /tmp is a link to the directory /var/tmp. When restoring to Server B, you must use the pipe var/tmp/nsr_pipe.

You can perform [parallel backups \[Page 29\]](#) using multiple pipes.

See also:

[Configuring the NetWorker Connection \[Page 23\]](#)



Setting Environment Variable NSR_ENV

One step in the [Configuration of the NetWorker Connection \[Page 23\]](#) is that you must set the environment variable **NSR_ENV** so that it contains the absolute path of the [configuration file \[Page 25\]](#).

If the environment variable **NSR_ENV** is not set, the system will attempt to use the file specified in the table as the configuration file:

Operating System	File
UNIX	/nsr/sapdb/env
Microsoft Windows	C:\Program Files\nsr\sapdb\env

Procedure

Follow the procedure described in [Setting environment variables \[Page 31\]](#).



Configuration File (NetWorker)

To be able to use the external backup tool NetWorker, you must create a configuration file as a step of the [Configuring the NetWorker Connection \[Page 23\]](#).

Procedure

You can define a parameter in the format `<key_word> <value>` in each line of the configuration file.

- `<key_word>`: A key word must be specified at the beginning of each line. Lines without one of the permissible keywords are ignored.
- `<value>`: Value of the parameter. If this value contains a blank character or another space character, place the value in quotation marks.

If you want to avoid a certain parameter being set by the configuration file, you must completely remove the corresponding line with the format `<key_word> <value>` from the configuration file.

You can use the following keywords to define parameters:

Keyword	Value
NSR_HOME	Absolute path of the directory in which NetWorker is installed. The NetWorker programs SAVE; MMINFO and RECOVER are stored in this directory.
NSR_HOST	Name of the NetWorker server to be used.
NSR_POOL	Name of the NetWorker tape pool to be used This parameter is optional. If you use the environment variable <code>NSR_POOL</code> Setting Environment Variables [Page 31] , the tape pool specified in this environment variable is used and the parameter specified in the configuration file is ignored.

NSR_EXPIRE	<p>Expiry date or expiry period for the backup This value is transferred to the NetWorker SAVE program. The permissible <value> entries are described in the NetWorker documentation. The parameter NSR_EXPIRE <value> is optional. If you use the environment variable NSR_EXPIRE Setting Environment Variables [Page 31]), the date or period specified in this environment variable is used and the parameter specified in the configuration file is ignored.</p>
NSR_NOTVERBOSE	<p>Specifies which of the NetWorker programs SAVE and RECOVER are started with the -v option. The following <value> specifications are permissible: NONE: Default setting. The NetWorker programs SAVE and RECOVER are started with the -v option. SAVE: The NetWorker SAVE program is started without the -v option, the NetWorker RECOVER program is started with the -v option. RECOVER: The NetWorker SAVE program is started with the -v option, the NetWorker RECOVER program is started without the -v option. "SAVE AND RECOVER": The NetWorker SAVE and RECOVER programs are started without the -v option.</p>
NSR_USEOUTPUT	<p>Specifies if the output of the NetWorker SAVE program should be analyzed during backups. The following <value> specifications are permissible: SAVE: Default setting. The output of the NetWorker SAVE program is checked for error messages. NONE: The output of the NetWorker SAVE program is not checked for error messages. Only the return code of SAVE is used. As the SAVE program can return the return code 0 even if an error has occurred, you should not use the parameter NSR_USEOUTPUT NONE.</p>
NSR_IGNOREERROR	<p>Character string <error_text> All error messages of the NetWorker SAVE program with the format <pipe_name>:<error_text> are ignored. You must make an NSR_IGNOREERROR entry for every error message that is to be ignored.</p>
NSR_EBIDTYPE	<p>Specifies whether restores should be performed with the Database Manager using the backup times as numbers or through the NetWorker Save Set Identifier The following <value> specifications are permissible: NSAVETIME: Default setting. Backups are identified using their backup time. This procedure has the advantage that the NetWorker RECOVER program does not require any operating system user rights. You should use this procedure. SSID: Backups are identified using the NetWorker Save Set Identifier. You should not use this procedure. If necessary, contact SAP for more information.</p>
NSR_SAVEINTERVAL	<p>Specifies how many seconds the system should wait between SAVE calls during parallel backups. Default setting: 60 seconds</p>

NSR_BACKUPNAME	<p>Name under which the backup is to be stored in NetWorker You can specify a character string of your choice in which the placeholders <database_name> and/or <server_node> can be used. When backing up/restoring with NetWorker, the placeholders are automatically replaced with the name of the database instance and/or the database server.</p> <p>Default setting: Database instance name</p>
NSR_AVOIDPSSIDBUG	<p>NO/YES</p> <p>A software error in the MMINFO program when using the option <code>-q pssid=0</code> (PSSIDBUG) is known as of NetWorker 6.0. This error can be avoided if the parameter NSR_AVOIDPSSIDBUG is set appropriately.</p> <p>NO: Default setting. Calls the NetWorker MMINFO program with the option <code>-q pssid=0</code></p> <p>YES: Avoids the software error in the MMINFO program (only NetWorker versions as of 6.0)</p>
NSR_SAVETIMEFORM AT	<p>Specifies a date format that is used for the analysis of the output of the NetWorker MMINFO program.</p> <p>Default setting: mm/dd/yy HH:MM:SS AM (for NetWorker date output that is 8 characters long)</p> <p>and</p> <p>Default setting: mm/dd/yyyy HH:MM:SS AM (for NetWorker date output that is 10 characters long)</p> <p>yy/yyyy years, mm months, dd days, HH hours, MM minutes, SS seconds, AM AM or PM</p> <p>You can only configure one date format.</p>
NSR_SIZEROUNDUP	<p>Specifies how the size specification for backups transferred with the NetWorker SAVE program is to be used.</p> <p>NOROUNDUP: Default setting. The size specification transferred by SAVE is used unchanged.</p> <p>FIRSTDECIMAL: The size specification transferred by SAVE is to be increased by 0.1 (For example: Backup size 14 GB is used with 14.1 GB).</p> <p>NORMAL: The size specification transferred by SAVE is increased by 0.5.</p> <p>LASTINTEGER: The size specification transferred by SAVE is increased by 1.</p> <p>This specification can be used as of the following SAP DB versions: 7.2.05.017, 7.3.00.021, 7.4.03.000</p>
NSR_AVOIDTIMEDEB UG	<p>Specifies a character string that is used as the value for the MMINFO option <code>-t</code>. In this way, you can use MMINFO versions that cannot be used without the <code>-t</code> option.</p> <p>The character string must match the format expected by MMINFO. If the character string consists of multiple values, place these in quotation marks.</p> <p>Note that backups that are not within the time span specified by the character string are regarded by SAP DB as no longer available for a restore.</p> <p>This specification can be used from the following SAP DB versions: 7.2.05.018, 7.3.00.022, 7.4.02.004, 7.4.03.000</p>

See also:

[Example Configuration File \[Page 28\]](#)



Example Configuration File (NetWorker)

The [configuration file \[Page 25\]](#) for a NetWorker connection can be explained using the following example.

Example

```

NSR_HOST          p47579
NSR_HOME          "C:\Program Files\nsr\bin"
NSR_POOL          SAPDBPOOL
NSR_EXPIRE        year

NSR_NOTVERBOSE    RECOVER
NSR_EBIDTYPE      NSAVETIME

NSR_USEOUTPUT     SAVE
NSR_IGNOREERROR   " unknown error 109 (0x6d) "
NSR_IGNOREERROR   " using unlocked access"

NSR_SAVEINTERVAL  60
NSR_BACKUPNAME    SAPDB:<database_name>_on_<node>

NSR_AVOIDPSSIDBUG YES
NSR_SAVETIMEFORMAT "yyyy/mm/dd HH:MM:SS AM"

```

Explanation

Keyword	Value	Explanation
NSR_HOST	p47579	The NetWorker server is running on server p47579.
NSR_HOME	"C:\Program Files\nsr\bin"	The NetWorker client is installed on the database server in the directory C:\Program Files\nsr\bin
NSR_POOL	SAPDBPOOL	Backups are stored in the NetWorker pool SAPDBPOOL.
NSR_EXPIRE	year	The backups have an expiration time of one year.
NSR_NOTVERBOSE	RECOVERY	The NetWorker RECOVER program is run without the -v option.
NSR_EDITTYPE	NSAVETIME	The backup time is used to identify backups.
NSR_USEOUTPUT	SAVE	The output of the NetWorker SAVE program is searched for errors during every backup.
NSR_IGNOREERROR	" unknown error 109 (0x6d) " " using unlocked access"	The messages <pipe_name>: unknown error 109 (0x6d) and <pipe_name>: using unlocked access are ignored for the corresponding pipes.
NSR_SAVEINTERVAL	60	The system waits 60 seconds between two SAVE calls during parallel backups.
NSR_BACKUPNAME	SAPDB:<database_name>_on_<node>	If the database name is, for example, DB72, the backups are created with the name SAPDB:DB72_on_p47579 in NetWorker.

NSR_AVOIDPSSIDBUG	YES	The PSSIDBUG of the NetWorker MMINFO program is avoided (only for NetWorker as of Version 6.0)
NSR_SAVETIMEFORMA T	"yyyy/mm/dd HH:MM:SS AM"	The NetWorker program MMINFO delivers date specifications in the specified format. Example: 2001/12/31 11:59:58 AM



Parallel Backups (NetWorker)

Prerequisites

You have configured the NetWorker connection in accordance with the specifications in [Configuring the NetWorker Connection \[Page 23\]](#).

The following table shows from which SAP DB versions parallel backups and restores are possible with NetWorker.

SAP DB Version	Build	SAP DB Tools for Parallel NetWorker Backups	SAP DB Tools for Parallel NetWorker Restores
7.2.05	004	DBMCLI	DBMCLI
7.3.00	009	DBMCLI, DBMGUI	DBMCLI
	015	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	025	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.3.32	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
7.4.02	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	011	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM
7.4.03	000	DBMCLI, DBMGUI	DBMCLI, DBMGUI
	002	DBMCLI, DBMGUI, Web DBM	DBMCLI, DBMGUI, Web DBM

See also:

User Manual: SAP DB, sections [Operating System Platforms](#), and [SAP DB Versions and Database Instance Types](#).

You must configure a media group with the [Database Manager](#), the individual members of which conform to the conventions described in [backup medium \[Page 24\]](#). In particular, every [media group name \[Page 30\]](#) must begin with `NSR`.

Parallel backups are only possible for data backups (complete and incremental).

Requirements

The NetWorker command `SAVE` or `RECOVER` is started for each pipe. NetWorker requires the exact name of each backup pipe for a restore. The media group must therefore be configured in exactly the same way during the restore as during the backup. This includes the order of the media in the media group.

The number of tape drives should be the same as the number of pipes used for the backup.

Set the NetWorker parameter `Target Sessions` for each tape drive to 1.

Procedure

If you want to perform a parallel backup or restore, follow the procedure described in the following documentation:

- *Database Manager GUI: SAP DB 7.4*, sections [Saving to a Group of Parallel Backup Media](#) and [Recovery](#).
- *Database Manager CLI: SAP DB 7.4*, sections [Commands for Backups](#) and [Commands for Restoring](#).



If a deadlock occurs during a parallel restore, you must import the backup sequentially (that is, from the individual media in the media group) using the Database Manager. Test this procedure.



Terms and Procedures

[Media Name \[Page 30\]](#)

[External Backup ID \[Page 31\]](#)

[Setting Environment Variables \[Page 31\]](#)

See also:

User Manual: SAP DB → [Definition of Terms](#)



Media Name

To perform a backup or a recovery with external backup tools, you use the [Database Manager](#). Which backup tool is used is determined by the Database Manager according to the media name or, in the case of parallel backups, according to the name of the media group.

Definition

To perform a backup action with external backup tools, a specially named backup medium or group of backup media is required. The following sequences of letters at the beginning of a media name/media group name determine which external backup tools are used for backups on this medium/group of media, or for restores from this medium/group of media:

Sequence of letters	Backup tool to be used (configuration information)
ADSM	TSM (see Configuring the TSM Connection [Page 11])
BACK	Backint for SAP DB (see Configuring the Backint for SAP DB Connection [Page 19]) Backint for Oracle (see Configuring the Backint for Oracle Connection [Page 13])
NSR	Networker (see Configuring the Networker Connection [Page 23])

See also:

The SAP DB Database System, section [Backup Medium](#)



External Backup ID

Every backup that was created with an external backup tool using a medium ([media name](#) [\[Page 30\]](#)) has its own unique identifier, the external backup ID.

See also:

User Manual: SAP DB, [External Backup ID](#) section

[Backup with External Backup Tools \[Page 5\]](#)

[Restore with External Backup Tools \[Page 6\]](#)



Setting Environment Variables

So that the [Database Manager](#) can access the environment variables that it requires on the database server, you must create these explicitly using a [DBM command](#).

Setting actual environment variables using operating system commands is therefore not applicable.

If only local accesses are made to a Database Manager in a purely Microsoft Windows NT environment, you can use normal Microsoft Windows NT environment variables.

Procedure

You can declare an environment variable or export it directly to the environment.

- You can declare an environment variable `<variable>` on the database server by entering the following DBM command :

```
dbmcli -d <database_name> -n <server_node> -u
<userid>,<password> dbm_configset -raw <variable> <value>
```

- You can export an environment variable `<variable>` to the environment with the Database Manager before calling an external backup tool. To do this, specify the following DBM command:

```
dbmcli -d <database_name> -n <server_node> -u
<userid>,<password> dbm_configset -raw set_variable_<number>
<variable>=<value>
```

(0<= number <=100)

The Database Manager exports the environment variable `<variable>` with the value `<value>` before an external backup tool is called.

Exporting an environment variable is supported as of the following SAP DB versions: 7.2.05.016, 7.3.00.021, 7.4.02.002, 7.4.03.000



Even if you have stored multiple values for an environment variable `<variable>`, only one value is exported for this environment variable.

Example:

You have entered the following DBM commands:

```
dbmcli ... dbm_configset -raw set_variable_<number1>
<variable>=<value1>
dbmcli ... dbm_configset -raw set_variable_<number2>
<variable>=<value2>
```

If `number1 < number2`, the Database Manager exports only value `<value1>` for the environment variable `<variable>`, otherwise only value `<value2>`.

If one of the environment variables TEMP, TMP, ADINT, ADA_OPT, NSR_ENV, NSR_POOL, NSR_EXPIRE, or BSI_ENV has been stored both with

```
dbmcli ... dbm_configset -raw <variable> <value>
```

and

```
dbmcli ... dbm_configset -raw set_variable_<number>
```

```
<variable>=<value2>
```

the environment variable <variable> is exported with the value <value>, before an external backup tool is called.

See also:

Database Manager CLI: SAP DB 7.4, [Changing a Database Manager Configuration Parameter](#) section.